

# Kiosk Mode

## Contents

## Overview

### Overview

A kiosk is a computer, tablet, or smartphone with settings that limit user access to certain apps and webpages. Usually, browser windows are full screen and the address, tools, menu, and status bars are hidden. For this reason, you may want to set up kiosks for patrons to use [Self-Service](#). That way, they can sign in and out without being able to do anything else on that device.

KeepnTrack is web-based, so you can access any module from any computer or tablet. All you need is the URL!

Learn how to set up kiosks on your device's specific operating system and internet browser.



Computer Kiosks

Set up a kiosk with a desktop or laptop.



Tablet Kiosks

Set up a kiosk with a tablet.

## Computer Kiosks

### Computer Kiosks

You can set up a desktop or laptop computer as a kiosk. Simply follow the directions for your operating system and browser.

---

### macOS

#### Configure your browser to run at startup

##### Login Items

Add your browser to your Login Items so it will automatically open when you start the computer. This will work for OS X Lion (10.7) through macOS Catalina.

1. Go to **System Preferences > Users and Groups** (or **Accounts** in some older versions).
2. Click on the user for which you want your browser to run at startup.
3. Select the **Login Items** tab.
4. Click on the **+** (plus) icon.
5. Select your browser and click **Add**.

##### Shell Scripts

Alternatively, you can set up a shell script that will automatically open Chrome in full-screen to a designated website.

1. Go to **Finder > Applications > Automator**.
2. Select **Application** and click **Choose**.
3. Double click on **Run Shell Script**.
4. Copy and paste the following text into the text box:  

```
/Applications/Google\ Chrome.app/Contents/MacOS/Google\ Chrome --app="https://ccdemo.goalexandria.com/librarian?" --kiosk --kiosk-printing --start-fullscreen
```
5. Replace `https://ccdemo.goalexandria.com/librarian?` with the link to the website you want Chrome to automatically open.
6. Click **File > Save**. Name the script and make sure the file format is **Application** before clicking **Save**.
7. Follow the Login Items instructions above to add this script to your startup items.



You may need to completely quit out of Chrome before testing or running this script for it to work properly.

## Set up kiosk mode

For those on macOS Catalina, you can use the

[Screen Time](#) app to set limits on apps and websites.

---

## Windows

### Configure your browser to run at startup

The following steps will work with Windows Server 2008, Windows 7, and Windows 10.

To make a web browser launch automatically during startup, create a shortcut to the browser and place it in the Windows **Startup** folder:

1. Click **Start** followed by (Windows System) **Run** and type:
  - %userprofile%\Start Menu\Programs\Startup
2. Please note that this location will only affect *your* user profile at startup; if you would rather have the browser launch at startup for *every* user who logs on to the computer, place the browser shortcut in this location instead:
  - %allusersprofile%\Start Menu\Programs\Startup
3. This opens the **Startup** folder for the current (or every) user profile.
4. Now you'll want to add a shortcut to the browser you want to open at startup in the folder.
  - a. Right-click inside folder and choose **New** followed by **Shortcut** and provide the path to the browser for which you want to execute at startup.
  - b. Drag the browser shortcut to the folder from your desktop or start menu.
  - c. Copy and paste the browser shortcut from a different location.
5. See *set up kiosk mode* to find out how to set up a special shortcut that opens the browser in full-screen kiosk mode.

### Set up kiosk mode

The following steps are for running Google Chrome in full screen kiosk mode on a Windows machine:

1. Right-click on your Windows **Desktop** and select **New** followed by **Shortcut**.
2. This opens the **Create Shortcut** window, asking you to **Browse** for the "chrome.exe" file.
3. Although it *can* be different (depending on your setup), the file is usually found here: C:/Program Files (x86)/Google/Chrome/Application/chrome.exe
4. Click **Next**.
5. Type a name for the shortcut (e.g. "Chrome Kiosk Mode") and click **Finish**.
6. Right-click on the new shortcut on your **Desktop** and go to **Properties**.
7. At the end of the **Target** field, following "chrome.exe", include this additional flag so it ends like the following: ...chrome.exe" --kiosk "[enter full URL here]"
8. Next, click **Apply** followed by **OK**.
9. If you would like to launch Google Chrome every time your machine restarts, copy the newly-created shortcut and paste it into your **Start up** folder. (See the *Configure your browser to run at startup* section above.)

Try these steps if your kiosk isn't working:

1. Make sure you've exited Chrome completely. It often has background processes running.
  - a. Close background processes by opening the Task Manager and ending Google Chrome processes.
  - b. Stop them from running when you exit the program by going to Chrome's **Settings > Advanced > System** and making sure *Continue running background apps when Google Chrome is closed* is set to off. This should also take care of bookmark bars showing on your kiosk.
2. Keep your Taskbar from showing by closing all other programs and changing its settings to both locked and automatically hidden on tablet/desktop.
  - a. Be warned users can still access Start by hitting the Windows key.



- Double-clicking on the newly-created shortcut will launch Google Chrome in full-screened Kiosk mode.
- To exit the Kiosk mode, press **ALT+F4** on your keyboard.
- The shortcut for **Full Screen** is **F11**; you can also click the **Wrench** icon in the top-right corner of the browser and select the **Full Screen** icon.
- When Google Chrome is running in full-screened Kiosk mode, the toolbars are *not* available; however, you are still shown a reminder at the top of the page that **<F11>** exits **Full Screen** mode.

The following steps are for running Firefox in full screen Kiosk mode on a Windows machine:

1. Right-click on your Windows **Desktop** and select **New** followed by **Shortcut**.
2. This opens the **Create Shortcut** window, asking you to **Browse** for the "firefox.exe" file.
3. Although it can be different (depending on your setup), the file is usually found here: C:\Program Files (x86)\Mozilla Firefox\firefox.exe
4. Click **Next**.
5. Type a name for the shortcut (e.g. "Firefox Kiosk Mode") and click **Finish**.
6. Right-click on the new shortcut on your **Desktop** and go to **Properties**.
7. At the end of the **Target** field, following "firefox.exe", include this additional flag: "firefox.exe -kiosk http://[enter URL here]".
8. Next, click **Apply** followed by **OK**.
9. If you would like to launch Firefox every time your machine restarts, copy the newly-created shortcut and paste it into your **Startup** folder. (See the *Configure your browser to run at startup* section above.)



- Double-clicking on the newly-created shortcut will launch Firefox in full-screened Kiosk mode.
- To exit the Kiosk mode, press **Alt+F4** on your keyboard.

---

## Chrome OS (Chromebooks)

Configure your browser to run at startup

You can

[customize your homepage and startup pages](#) on Chromebooks.

Set up kiosk mode

Chromebooks now use

[Family Link](#) to manage app and website access for specified Google accounts.

[Link](#)

## Tablet Kiosks

### Tablet Kiosks

Set up a kiosk with a tablet. Simply follow the directions for the type of device you have.



We do not recommend setting up KeepnTrack kiosks on smartphones.

---

## iOS (iPad)

Save a webpage as an app

Save your Attended, Express, and Self-Service Kiosk links as apps on your device. Then you just have to simply click on the app to open that webpage in Safari!

1. In Safari, go to the webpage you want to save as an app.
2. Tap on the square and arrow icon at the bottom of the screen.
3. Tap **Add to Home Screen** and customize the name.
4. Tap **Add** when you're done.



Safari is currently the only internet browser in iOS that can save webpages as apps.

Restrict access on devices

You can use [Guided Access](#) in Accessibility Settings to limit your Apple devices to one app and control which features are available.

---

## Android

### Save a webpage as an app

Save your Attended, Express, and Self-Service Kiosk links as apps on your device. Then you just have to simply click on the app to open that webpage!

1. In Chrome, go to the webpage you want to save as an app.
  2. Tap the three-dot menu in the upper right-hand corner of the screen.
  3. Tap **Add to Home screen** and customize the name.
  4. Tap **Add** when you're done.
- 
1. In Firefox, go to the webpage you want to save as an app.
  2. Tap the three-dot menu in the upper right-hand corner of the screen. (This may be at the bottom of the screen.)
  3. Tap **Page**.
  4. Tap **Add Page Shortcut**.
  5. Place the shortcut on your home screen by either dragging the icon to where you want it or tapping **Add**.

### Restrict access on devices

You can either

[pin screens](#) or use [lock task mode](#) to limit your Android devices to one app and control which features are available.